

Thank you for purchasing FX Turbine! We wish you to get a good profit with us!

Please follow the instructions below to install the EA and prepare it for a proper work.

- Open MetaTrader4 > click on File > Open Data Folder > double click the MQL4 folder. In case you have UAC settings disabled, the folder location will be:


C:\Users\[user name]\AppData\Roaming\MetaQuotes\Terminal\[32 character long MT4 ID]\MQL4

- Copy the files from the archive you got to the correct directories of MetaTrader 4:

FX Turbine.ex4 to C:\Users\[user name]\AppData\Roaming\MetaQuotes\Terminal\[32 character long MT4 ID]\MQL4\Experts
turb.dll to C:\Users\[user name]\AppData\Roaming\MetaQuotes\Terminal\[32 character long MT4 ID]\MQL4\Libraries


- Close MetaTrader 4 and reopen it.

- Under the "Navigator" window you should find FX Turbine inside the "Expert advisors" drop down menu. ----->



- Drag-and-drop (press the left mouse button to drag and un-hold to release) the EA in your chart, or right click on the Expert Advisor and selected "Attach to chart".

- Finally, if all the steps above are performed correctly you should be able to access the EA' settings and click "Allow DLL imports" and "Allowing live trading" to enable your EA. ----->



- Change settings, if needed:

AutoRisk (default value = true) - Auto calculation of a lot size. It depends on the next parameter - **SetRisk**.

SetRisk (default value = 50) - A part of the deposit, which you are going to risk (sets in a percent).

Compounding (default value = false) – Account balance grows exponentially due to the compounding of profits (for advanced usage only).

Lots (default value = 0.1) - Manual input of a lot size, in case if **AutoRisk** is disabled (false).

FindGMT (default value = true) - Auto detection a GMT of your broker.

SetGMT (default value = 1) - Manual input of GMT, in case if **FindGMT** is disabled (false).

Identifier (default value = 8744413) – Magic number of each EA's order (needed for trading with different EAs at the same time).

Slip (default value = 15) - Slippage (for advanced usage only).

- Recommended settings are the **default values** of the EA's parameters.

- FX Turbine works only on Time Frame **M30** on the next currency pairs: **EURJPY, EURUSD, AUDUSD**.

- Minimal recommended deposits (**SetRisk=50**):

EURJPY - 400\$ and for 0.01,

EURUSD - 310\$ for 0.01,

AUDUSD - 280\$ for 0.01.

Minimal possible deposits (**SetRisk=100**):

EURJPY - 200\$ and for 0.01,

EURUSD - 155\$ for 0.01,

AUDUSD - 140\$ for 0.01.

- Minimal recommended leverage is **1:200**. Minimal possible leverage is 1:100.

- FX Turbine should trade **24/5** for a proper work.

Contact us: support@fxturbine.com